




HEWLETT-PACKARD 9830A CALCULATOR 11270B MATRIX OPERATIONS ROM

OPERATING MANUAL



OPERATING MANUAL



Copyright by Hewlett-Packard Company 1972

HP Computer Museum www.hpmuseum.net

For research and education purposes only.

TABLE OF CONTENTS

CHAPTER 1: INTRODUCTORY DESCRIPTION

EQUIPMENT SUPPLIED	ъ. н. т.					×	+	2	м	×	,	,	н	×	*	v	٠	*	v	1-1
INSPECTION PROCEDURE	к х н	2	,		+		٠		9			л				*	*	e		1-1
INSTALLING THE PLUG-IN	BLOCK		*	,									5			*		×	+	1-1
OTHER REQUIREMENTS	- E - F			ч		,		~					x			£		e.	×	1-1

CHAPTER 2: CHARACTERISTICS OF MATRICES

MATRIX NAMES	٠		ж	4	e.	×	,		0		v		Υ.	e	~			,		2-1
MATRIX DEFINITION	٠	,			+	•			×	4		,				4	+	ψ	Ŧ	2-2
MATRIX BOUNDARIES		>		÷	65	,	v		0	^	e	+	÷	£.	×	×	5	×		2-3

CHAPTER 3: INPUT AND OUTPUT OF MATRICES

THE INPUT STATEMENT		-	π.	×	*	,	×	~			•	•	,				+	٠	×			3-1
THE READ STATEMENT	~	+	5	ж	*	,	н	~	+	я	×	4						۰		٠	*	3-1
THE PRINT STATEMENT			×		+		×		ж		÷	я	A	-	7	±	C'		-	3		3-1
THE MAT READ STATEMEN	ΝT								×	N	é			,	z	8	5	×			4	3-2
THE MAT PRINT STATEME	NΤ	•		×							×		*				×		н	н		3-2

CHAPTER 4: MATRIX OPERATIONS

	*			-			~														н	4-1
SUBTRACTION OF MATRIC	ES		-	+					~	¢		×		,		ч			х.		*	4-2
SCALAR MULTIPLICATION	OF	= N	ΛA	TF	RIC	CE:	S	×	~	۰	,		,		,		v	4	+		н	4-2
COPYING MATRICES	×							~		7	4					-	*				4	4-2
EXAMPLE 1							*			×	-	×				,			,	~		4-3
MATRIX MULTIPLICATION			•	ų	,				e	4	×				,		2	-			,	4- 4
TRANSPOSITION OF MATR																						4-6
EXAMPLE 2	4			v					7		×											4-8
THE CONSTANT MATRIX							*			8	÷				,	٢						4-9
THE REDIM STATEMENT																						4-10
EXAMPLE 3																						4-12
THE ZERO MATRIX																						4-13
THE IDENTITY MATRIX				-		-				~						<i>,</i>	,				· .	4-14
INVERSION OF MATRICES																	4		-	-		4-1 4
DETERMINANTS																					*	4-16
EXAMPLE 4																					•	1 16
		٠	٠	*	*	•	*	٠	•	÷	<	^	×	۲	*		*	-	N		. "	+-10

APPENDIX

DIAGNOSTIC NOTES				3	,	÷		,			,	*			4			£	,	,	y	ų		A-	1
------------------	--	--	--	---	---	---	--	---	--	--	---	---	--	--	---	--	--	---	---	---	---	---	--	----	---

PREFACE

The Matrix Operations Read-Only-Memory (ROM) can be purchased as an accessory plug-in block or as an internal modification to the calculator.

The Plug-in Version:

The 11270B Matrix Operations ROM block is installable by the user. It plugs into any of the five slots behind the ROM door on the left side of the calculator.

The Calculator Modification:

The Option 270 Matrix Operations ROM must be installed by qualified HP personnel. When it is installed, a decal showing the option number (Option 270) is attached to the inside of the ROM door.

Should you wish to add the option after you have received your calculator, please order accessory number HP 11270F from the sales office nearest to you (see the inside back cover of this manual). The Option 270 will then be installed for you by our field personnel.

Once either version of the ROM (the plug-in block or the internal modification) has been installed, the operation is identical. Therefore, this manual makes no further distinction between the two types of ROM.

Chapter 1

INTRODUCTORY DESCRIPTION

The Matrix Operations Read-Only-Memory (the Matrix ROM) provides additional capabilities to the Model 30, permitting mathematical operations upon matrices, useful in physics, engineering and statistics operations. It also provides special programming techniques useful in processing any kind of data in tabular or array form.



One Operating Manual, -hp- Part Number 09830-90004, is supplied with the Matrix ROM.



Refer to Appendix A in the 9830A Calculator Operating and Programming Manual for the procedures used to verify the operation of ROM's.



The complete procedure to install a plug-in block is in the Operating and Programming Manual for the 9830A Calculator. Following are some reminders:

The block can be installed in any of the five ROM slots.

Switch the calculator off before installing or removing a block.

The label on the block should be 'right-side-up' and facing the ROM door when the block is properly installed.

Ensure that the block is properly mated to the connector at the back of the slot before switching the calculator on.



It is assumed that you are already familiar with BASIC programming and with the operating procedures for the HP 9830A Calculator.



Chapter 2

CHARACTERISTICS OF MATRICES

A table of data, or any collection of data elements arranged in rows and columns, is known as a matrix. A list of data, or any collection of data elements arranged in a single column or row, is known as a vector.

Here is an example of a matrix:

GRADE	BOYS	GIRLS
1	10	7
2	9	8
3	9	10
4	7	9
5	7	10
6	9	11

Here is an example of a vector:

TEST SCO	RES
93	
85	
79	
89	
68	
95	
100	



A matrix name consists of any single letter from A through Z, hence, up to 26 matrices can be assigned at the same time in one program.

******* MATRIX DEFINITION ******

To reserve storage space for arrays (matrices and vectors), a DIM or COM* statement is used. Arrays not mentioned in a DIM statement are assumed to have 10 elements if they are one-dimensional, or 10 rows and 10 columns if they are two-dimensional.

The number of elements in a vector, or the number of rows or columns in a matrix, must be specified as an integer from 1 to 256 in a DIM statement as:

	"你们们不是你不能不能不是你的你的,我们不是你的你的?""你们的你的你?""你们的你们,你不是你是我们的你的。""你们你?""你们,你们不是你的吗?""你们,你不 "你们,你们们你们,你们们你不是你不是你的?""你们,你们你们你们你们?""你们,你们们你们,你们们你们们?""你们,你们们你们?""你们,你们们不是你们,你们不 "你们""你们"""你们?""你们?""你们?""你们?""你们?""你们?""	
IN TIM AFIND.		
an bad ang da Lit i Dia an bad sa an ang ang ang ang ga ga		
- 30 DIM CL20,2		
	27 The gradient of the first second s Second second s Second second sec second second sec	

In statement 10 above, Array A is a column vector of 100 row elements.

In statement 20, Array B is dimensioned 75 rows by 5 columns. This row-column convention exists throughout this manual.

In statement 30, Array C has the same number of rows and columns, and is square. A square matrix is any matrix having the same number of rows and columns. Some matrix operations, such as inversion, can be performed only on square matrices.

Generally, the operations which apply to matrices also apply to vectors. So it is convenient to think of a column vector of n elements as an 'n by 1' matrix, and a row vector of n elements as a '1 by n' matrix.

In this manual, arrays, whether they are one-dimensional or two-dimensional, are referred to as matrices. A distinction is made only when special rules apply to the use of vectors.

Space can be saved when *storing* large quantities of array data by specifying integer or split precision. This is because while full (normal) precision requires four words of calculator memory per array element, split precision requires two words and integer precision requires only one word per array element. Split and integer precision are specified in the DIM statement as shown below.

10 DIM ASE200,5] 20 DIM BIE100,14]

Although calculator memory space can be saved when storing data by using integer and split precision, the determinant and inverse of a matrix should be performed only on full precision matrices. This is because, when integer and split precision are specified, errors due to reiterative internal rounding are multiplied during complex operations and often contribute to illogical results. Therefore, specify full precision matrices whenever possible, split precision with the greatest care, and avoid integer precision when inverting or finding the determinant of a matrix.

^{*} The COM statement can also be used to reserve storage space for arrays, but must be the first statement entered into the calculator memory. Refer to the Model 30 Operating and Programming Manual for more information about the COM statement.



The working size of a matrix can be smaller than its physical size, which is the space reserved in the DIM statement. For example, a matrix specified 20 by 20 in a DIM statement can be used to store fewer than 400 data elements; the DIM statement supplies only an upper bound on the number of elements.





Chapter 3

INPUT AND OUTPUT OF MATRICES

This chapter describes some of the methods for storing a table or a list of data in a matrix and for printing a table or list of data from a matrix.



The INPUT statement, with the FOR and NEXT statements, makes it easy to enter a matrix from the keyboard. The following instructions enable a 5 by 3 matrix to be entered one row at a time.

10 DIM AL5.31 20 FOR J=1 TO 5 30 INPUT ACJ, 13, ACJ, 23, ACJ, 33 40 NEXT J 🔶 THE READ STATEMENT 🗢

You can include the values to be stored in a matrix in program DATA statements, and can use the READ statement, with the FOR and NEXT statements, to read the matrix. With the following instructions, a 3 by 2 matrix is read.

10 DIM AE3,23 20 DATA 12,10,5,3,14,7 30 FOR M=1 TO 3 40 FOR N=1 TO 2 50 READ AEM,N3 60 NEXT N 70 NEXT M



The PRINT statement provides control in printing of headings and other information with a matrix. Using the following instructions, the data in the 3 by 2 Matrix A, above, can be printed and labeled.

80 PRINT "GRADE BOYS GIRLS" 90 FOR M=1 TO 3 100 PRINT M;AEM,1];AEM,2] 110 NEXT M ★ ★ ★ ★ THE MAT READ STATEMENT ★ ★ ★ ★ ★

Syntax:

MAT READ matrix name [(expression[,expression])] ...

Although matrix values can be assigned individually by using the READ statement, the MAT READ statement is easier to use because it causes an entire matrix to be read. To read a 3 by 2 matrix with the MAT READ statement:

10 DATA 12,10,5,3,14,7 20 MAT READ A[3,2]

The MAT READ statement causes the matrix to be filled from the DATA statement in the conventional row-column order: 1,1; 1,2; 2,1; and so forth.

10 MAT READ A 20 MAT READ X[6] 30 MAT READ M[N,P] 40 MAT READ C,D,E[6,N]

A new working size (an implicit REDIM statement - see Chapter 4) may be specified, as in statements 20 and 30 above, but must be within the limits of the DIM statement.

If no size specification is included, as in 10, above, the working size of the matrix is assumed to be its current physical size. If your program does not contain a DIM specification and the working size is not specified in the MAT READ statement, a 10 by 10 matrix is assumed and the first 100 elements in the DATA statement are used, or a 10 element vector is assumed and the first 10 elements in the DATA statement are used. For example, the statement A(5) = 32 causes a vector to be assumed.

More than one matrix name can appear in a MAT READ statement, as in statement 40, above.



Syntax:


MAT PRINT matrix name [,matrix name] ...

Although a matrix can be printed element-by-element by using a PRINT statement, the MAT PRINT statement is easier to use. The MAT PRINT statement causes an entire matrix to be printed row by row. Each row starts a new line, but when all the elements in a row will not fit in one line, the elements overflow into additional lines. Each row is separated by a blank line.



The spacing between row elements is controlled by the use of the comma or the semicolon. The comma causes the matrix to be printed with five elements per line, while the semicolon causes the matrix to be printed with up to twelve elements per line. The punctuation after the matrix name determines its spacing on a page. If there is no punctuation the matrix is printed with five elements per line.

A one-dimensional array, or column vector, is printed one element per line with double spacing between lines.



Chapter 4

MATRIX OPERATIONS

The operations discussed in this chapter are designed specifically for use with matrices. However, all BASIC language operations that can be performed on simple variables can also be performed on array variables or matrix elements; such as IF, WRITE, SQR, ABS, etc.



Syntax:

MAT matrix name = matrix name + matrix name

The corresponding elements of two matrices can be added by using a MAT (Matrix) command:

110 MAT C=A+B

The actual dimensions of A,B and C must be the same. Each element in A is added to the corresponding element in B and the result is stored in the corresponding position in C.

Calculator memory space can be saved if the result is accumulated in one of the matrices already containing data, such as Matrix X in:

120 MAT X=X+Y

Each element in Y is added to the corresponding element in X and the result is contained in X.

If Matrix A is a 2 by 3 matrix containing:

3	6	2
4	1	5

and Matrix B is a 2 by 3 matrix containing:

2	4	7
5	3	1

Then, if the statement MAT C=A+B is executed, Matrix C contains:

4-1

5 10 9 9 4 6



Syntax:

MAT matrix name = matrix name - matrix name

The corresponding elements of two matrices can be subtracted:

110 MAT C=A-B 120 MAT X=X-Y

As in the addition of matrices, all three matrices must have the same actual dimensions.



Syntax:

MAT matrix name = (expression) * matrix name

Each element in a matrix can be multiplied by a number or by the value of any arithmetic expression. The number or expression must be enclosed in parentheses and must precede the matrix name:

110 MAT A=(5)*A 120 MAT X=(N/3)*Y 130 MAT P=(SQR17+3作私)#R

Each matrix must have the same actual dimensions if more than one matrix is named. In statements 120 and 130, above, N is a simple variable.



Syntax:

MAT matrix name = matrix name

For an exact copy in Matrix A from Matrix B:

110 MAT A=B

Each matrix must have the same actual dimensions.



Below are two tables containing the Math, Science, and Reading grades achieved by five students during two quarters of one school year.

	First	Quarter			Second Quarter									
Student No.	Math	Science	Reading	Student No.	Math	Science	Reading							
1	80	85	78	1	78	81	80							
2	71	80	72	2	73	82	88							
3	97	92	83	3	93	90	85							
4	77	82	98	4	81	88	94							
5	93	94	98	5	91	90	84							

We will use the grades in the first quarter for Matrix A, and in the second quarter for Matrix B:

Μ	atrix A	۹:	Ν	/latrix	B:
80	85	78	78	81	80
71	80	72	73	82	88
97	92	83	93	90	85
77	82	98	81	88	94
93	94	98	91	90	84

If the statement MAT C=A+B is executed, Matrix C contains:


166	158
162	160
182	168
170	192
184	182
	162 182 170

The grades for each student in each class have been added. We can now find the average of the two term grades for each student in each class:

110 MAT C=(1/2)*C

An expression and a scalar multiplication are used here; the result in C is now:

79	83	79
72	81	80
95	91	84
79	85	96
92	92	91



ł

·	Average Mic	l-Year Grades	
Student No.	Math	Science	Reading
1	79	83	79
2	72	81	80
3	95	91	84
4	79	85	96
5	92	92	91

NOTE Only one operation is performed in a MAT command. You cannot say MAT A = (1/2) * B + C, but must perform two separate steps: MAT A=(1/2) * BMAT A=A+C

Syntax:

MAT matrix name = matrix name * matrix name

Matrices can be multiplied only when the number of columns in the first matrix equals the number of rows in the second matrix.

110 MAT C=A*8

The matrix to the left of the equals sign must not appear to the right of the equals sign, (i.e., you cannot say MAT X=X*Y).

Unless you have already been introduced to matrix multiplication, you might assume that standard arithmetic rules are followed; however, this is not the case. In matrix multiplication, for MAT C=A*B, the elements in each column of Matrix B are multiplied by the corresponding elements in each row of Matrix A. The row products are then added together and stored in the appropriate row and column of Matrix C. Following are several examples of matrix multiplication.

Below is a table of ticket sales for four bus routes, and a table of ticket prices for the three kinds of tickets. Matrix multiplication can give you the total sales for each route.

Table A.	. Ticket Sal	es by Rou	te	Table B. Ticke	t Prices
	Single	Round			
Route	Trip	Trip	Commuter		
1	143	200	18	Single Trip	.25
2	49	97	24	Round Trip	.45
3	314	77	22	Commuter	18.00
4	82	65	16		

Here are the instructions to read the values in Tables A and B into Arrays A and B, respectively, and perform the matrix multiplication (MAT C=A*B).

```
10 DIM AL4,3],BL3],CL4]
20 DATA 143,200,18,49,97,24,314,77,22,82,65,16
30 DATA 0.25,0.45,18
40 MAT READ AL4,3],BL3]
50 MAT C=A*B
55 FIXED 2
60 MAT PRINT C
```

After A and B have been multiplied, Matrix C contains the total sales, in dollars, for each route: C(1) contains sales for Route 1, C(2) contains sales for Route 2; and so forth.

Matrix C:	449.75	(.25*143+.45*200+18*18)
	487.90	(.25*49+.45*97+18*24)
	509.15	(.25*314+.45*77+18*22)
	337.75	(.25*82+.45*65+18*16)

In the above example, a 4 by 3 matrix, Matrix A, is multiplied by a 3 by 1 matrix, Matrix B, giving a 4 by 1 matrix, Matrix C.

Suppose a price change is being considered, and Matrix B contains two columns of ticket prices:

	Old Price	New Price
Single Trip	.25	.30
Round Trip	.45	.50
Commuter	18.00	17.00

Then Matrix A, a 4 by 3 matrix, multiplied by Matrix B, a 3 by 2 matrix, results in Matrix C, a 4 by 2 matrix:

449.75	448.90	(.30*143+.50*200+17.00*18)
487.90	471.20	(.30*49+.50*97+17.00*24)
509.15	506.70	(.30*314+.50*77+17.00*22)
337.75	329.10	(.30*82+.50*65+17.00*16)

Here are the instructions to perform this multiplication. Note that the DATA in statement 30 has been rearranged.

10 DIM AE4,3],BE3,2],CE4,2] 20 DATA 143,200,18,49,97,24,314,77,22,82,65,16 30 DATA 0.25,0.3,0.45,0.5,18,17 40 MAT READ AE4,3],BE3,2] 50 MAT C=A*B 55 FIXED 2 60 MAT PRINT C



Mathematically, the product of two matrices, MAT C=A*B, is represented as follows:

$$C(I,K) = \sum_{J=1}^{N} A(I,J) * B(J,K)$$

Where N is the number of columns in Matrix A, and rows in Matrix B.

For any matrix multiplication, MAT C=A*B, if the dimensions of A=(P,N) and B=(N,Q), the result is a matrix of dimensions (P,Q). For example, a 5 by 4 matrix multiplied by a 4 by 1 matrix results in a 5 by 1 matrix. Remember that the value of N, above, must be the same in the two matrices: you cannot multiply a 5 by 3 matrix by a 5 by 3 matrix, but you can multiply a 5 by 3 matrix by a 3 by 5 matrix, or you can multiply a 3 by 5 matrix by a 5 by 3 matrix. However, the result of MAT C=B*A is not necessarily the same as MAT C=A*B.



Syntax:

MAT matrix name = TRN (matrix name)

The transposition of a matrix causes the rows in the matrix to become columns, and the columns to become rows:

110 MAT A=TRN(B)

The same matrix cannot appear on both sides of the equals sign. The actual dimensions of the transposed matrix must equal the reverse of the dimensions of the original matrix, that is, if the dimensions of B=(P,Q), transposition of Matrix B results in a matrix of dimensions (Q,P).

The transposition of:

	2 4	3 5	
		7	
is:		4 6 5 7	

Row 1 in the first matrix becomes column 1 in the second. Then row 2 becomes column 2 and so on.

Below are some examples which make use of matrix transposition.

Suppose you have a table of quantities of three product lines sold at four locations, and a second list consisting of prices for each product line.

Table	A. Product	Sales by Lo	cation	Table B. Pro	duct Prices
Location	Prod 1	Prod 2	Prod 3	Product	Price
1	7	2	6	1	5
2	3	8	9	2	2
3	10	5	4	3	1
4	3	1	2		

Table A is read into Matrix A, and Table B is read into Matrix B with the following instructions:

10 DIM AC10,10],BC10,10],CC4,1] 20 MAT READ AC4,3],BC3,1] 30 DATA 7,2,6,3,8,9,10,5,4,3,1,2,5,2,1

Now the two matrices can be multiplied to determine the total sales for each location:

40 MAT C=A+B

Matrix C is now a column vector containing 4 elements. C(1,1) is the sales at location 1, C(2,1) is the sales at location 2, and so forth.

To obtain a printout of sales by product at each location, and the total sales at each location, both of these matrices must be transposed:

50 DIM DE3,43,EE1,43 60 MAT D=TRN(A) 70 MAT E=TRN(C)

Now headings and data can be printed:

```
80 PRINT "LOCATION 1 LOCATION 2 LOCATION 3 LOCATION 4"
90 MAT PRINT D
100 PRINT "TOTALS"
110 MAT PRINT E
```

•••• EXAMPLE 2

A magazine publishing company has a table of distribution for magazines by region.

Table A. Ma	gazine Distributi	on by Region
Region	Magazine A	Magazine B
- Ī	200	50
2	150	45
3	250	60

A table of magazine cost-per-copy is used to determine the amount invested in each region:

Table B. Cost-per-copy by Magazine

Magazine	Cost-per-copy
A	.32
В	.18

Here is a program used to read the data and perform matrix multiplication to determine magazine cost by region.

```
10 DIM A[3,3],B[2,1],C[3]
20 MAT READ A[3,2],B
30 DATA 200,50,150,45,250,60,0.32,0.18
40 MAT C=A*B
50 FOR I=1 TO 3
55 FORMAT "REGION",F2.0," COST",F6.2
60 WRITE (15,55)I,C[]
70 NEXT I
```

Here is the result:

REGION 1 COST 73.00 REGION 2 COST 56.10 REGION 3 COST 90.80

The data contained in Matrix A is now to be used to determine the number of complimentary copies to be allotted to each region. A table of percentages by region is used:

Table D: % Complimentary Distribution by Region

Region	% Complimentary
1	15
2	13
3	21

4-8

т. Т.

Computer

Museum

The data from table D is contained in Matrix D. To perform a matrix multiplication, the columns in the first matrix must match the rows in the second matrix, (i.e., both must represent 'region'). To meet this requirement, Matrix A is transposed and stored in Matrix E. Here are additional program steps for this second matrix multiplication.

```
90 DIM DE3,1];EE2,3];FE2]
100 DATA 0.15;0.13;0.21
110 MAT READ D
120 MAT E=TRN(A)
130 MAT F=E*D
140 PRINT "MAGAZINE A COMPLIMENTARIES";INT(FE1])
150 PRINT "MAGAZINE B COMPLIMENTARIES";INT(FE1])
```

Here is the result:

			1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1		
MAGAZINE	P.	COMPL	IMENTI	<u> ARIE</u>	S 102
MAGAZINE	Β (COMPL	IMENTI	ARIE	\$ 25



Syntax:

MAT matrix name = CON [(expression[, expression])]

A constant matrix is any matrix with all elements equal to 1.

The statement MAT B=CON(3,3) results in the following 3 by 3 matrix:

1	1	1
1	1	1
1	1	1

Since 1 has a logical value of 'true', the constant matrix is useful for logic initialization.

If no subscripts are given, the constant matrix has the most recent dimensions specified. If subscripts are given, they cause the array to be dimensioned to the specified size.

One example of the use of a constant matrix, in summarizing a table of data, follows on page 4-12.

******* THE REDIM STATEMENT ******

Syntax:

REDIM (expression[, expression])

The working size of a matrix is the same as the physical size unless otherwise specified. To change the working size, a size specification is included in a MAT READ, CON, ZER, IDN or REDIM statement.

NOTE When a new working size is specified for a matrix containing data, the data is rearranged.

The following instructions create Matrix A:

10 DIM AC20,201 20 MAT READ AC2,31 30 DATA 4,7,9,5,8,10 40 MAT PRINT A;

Matrix A:

7 -5 8 10

Matrix A has a working size of 2 by 3. The following REDIM statement changes the working size to 3 by 2.

			しょう しょうせい きいち ふち さん いちち やめき 愛え みんかんかい しょうちょう ちょうやく	
		きごちょう ちちょう かいみん	- デージョン デージョン ション アンドウ サインション シャンション ション・ション・ション・ション ション・ション ション ション ション ション ション・ション ション・ション ション・ション ション・ション	
	and a second state of the second	·····································	マロズダン チャンデオャッキュ ひょうしょうしょう しょう しょう しょうしょう しょうしょう	1.1. A. K. M.
tere for the for the first	Y 6.4	and a second		2 I C A A L
in the life		- 1946 - 1947 - 1947 - 1947 - 1948 - 1948 - 1948 - 1948 - 1948 - 1948 - 1948 - 1948 - 1948 - 1948 - 1948 - 1948	医白喉病 解剖子 医黄疸素白白 医外口口 医口口口口 计分子 计分子 计分子	
11P1 B C D	1 84 - 446 - 642	The first of the second s		
	mit time we		2029 2 1 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2	
	and don't the board states	Definition of the second second second		トラアメルト やう
		(1) South and the second se	こうこう こうさい そうかん さち ゆうち かん ひかり しょうほう しょういい しょう アイト	1. 1. 1. 1. 1. 1. A. 1. J. 1.
he [4] [2] per [the part of the part of the		デブ・ボデル かえん アメリカ・ション・リーン しょうしん アイト・ディー・ション	
	4			
		- 2 合う	化学学学学学校学习学学校学习学习学校 医白白白白白白白白白白白白白白白白白白白白白白白白白白白白白白白白白白白白	
	1 F K 2 - 1	The second s		
		and the second	A State of the second secon	

Matrix A is now:

4 7 9 5 8 10

When you have a large program, a matrix which is no longer used can be redimensioned, thus using the same space in the calculator a second time.

Matrix A is a 2 by 4 matrix containing student absences for the school year as follows:

	First Quarter	Second Quarter	Third Quarter	Fourth Quarter
Boys	62	85	73	81
Girls	70	87	65	83

The average of absences for boys and girls for the school year is calculated:

10 DIM CE2:1] 20 MAT READ AE2:4] 25 FIXED 0 30 DATA 62:85:73:81:70:87:65:83 40 MAT B=CONE4:1] 50 MAT C=A*B 60 MAT C=(1/4)*C 70 PRINT C=(1/4)*C 70 PRINT "AVERAGE ABSENCES" 80 PRINT " BOYS GIRLS" 90 PRINT CE1:1];CE2:1]

Matrix A is now to contain total enrollment by month, and average enrollment is to be calculated:

100 REDIM AE1,9] 110 FOR M=1 TO 9 120 DISP "ENTER MONTHLY ENROLLMENT"; 130 INPUT AE1,M] 140 NEXT M 150 REDIM BE9,1],CE1,1] 160 MAT B=CONE9,1] 170 MAT C=A*B 180 MAT C=(1/9)*C 190 PRINT "AVERAGE ENROLLMENT" 200 MAT PRINT C

Another use of the REDIM statement is shown later in Example 4, lines 40 to 90, where a matrix initially contains two rows of elements supplied by a MAT READ statement. After the REDIM statement is used, the matrix contains four rows of elements; and the values of the elements in the third and fourth rows of the matrix are obtained from calculations. **EXAMPLE 3**

Suppose you have a table of inventory values by stock number at five branch stores, as in Table A, below.

Table A. Inventory Value					
Stock Number	Branch A	Branch B	Branch C	Branch D	Branch E
1	52.80	35.20	31.68	26.40	26.40
2	37.50	31.25	25.00	23.75	18.75
3	8.25	6.60	6.60	4.95	3.30
4	11.76	10,50	8.40	8.40	6.30

The following instructions are used to establish the 4 by 5 matrix, Matrix A, then to calculate and print the total inventory value for each stock number.

10 DIM AE4,5],BE5,1],CE5,1] 20 DATA 52.8,35.2,31.68,26.4,26.4 30 DATA 37.5,31.25,25,23.75,18.75 40 DATA 8.25,6.6,6.6,4.95,3.3 50 DATA 11.76,10.5,8.4,8.4,6.3 60 MAT READ AE4,5] 70 MAT B=CONE5,1] 80 REDIM CE4,1] 90 MAT C=A*B 100 PRINT "TOTAL INVENTORY VALUE BY STOCK NUMBER" 110 FOR I=1 TO 4 120 FORMAT F10.0,F8.2,/ 130 WRITE (15,120)1,CEI,1] 140 NEXT I

Matrix A is multiplied by the constant matrix, Matrix B, to give the total value across each row in A: 1*52.80+1*35.20+1*31.68, and so forth.

The following instructions use the above Matrix A, and calculate and print the total inventory value for each branch store.

150 DIM D[5,4],E[1,5] 160 REDIM C[5,1] 170 MAT D=TRN(A) 180 MAT B=CON[4,1] 190 MAT C=D*B 195 FIXED 2 200 PRINT "TOTAL INVENTORY VALUE BY STORE" 210 PRINT "TOTAL INVENTORY VALUE BY STORE" 210 PRINT "STORE A STORE B STORE C"; 215 PRINT "STORE A STORE D STORE E" 220 MAT E=TRN(C) 230 MAT PRINT E

In these instructions, Matrix C is transposed before it is printed. The stores can then be used as column headings so that the results are easily identified.

++++ THE ZERO MATRIX +++

Syntax:

MAT matrix name = ZER [(expression[,expression])]

A zero matrix is any matrix with all elements equal to zero.

The statement MAT B=ZER(3,3) results in the following 3 by 3 array:

0	0	0
0	0	0
0	0	0

Since 0 has a logical value of 'false', the zero matrix is useful for logic initialization.

If no subscripts are given, the zero matrix has the most recent dimensions specified. If subscripts are given, they cause the array to be dimensioned to the specified size.

Here is an example of the use of the zero matrix. Table A contains the grades received in Reading by 20 students. Below is a program to read the grades and print out the number of students receiving each grade.

Table A. Student Grades in Reading

Grade	Student	Grade
93	11	52
85	12	66
79	13	80
89	14	79
68	15	98
95	16	95
100	17	89
66	18	68
79	19	72
85	20	96
	93 85 79 89 68 95 100 66 79	9311851279138914681595161001766187919

10 DATA 93,85,79,89,68,95,100,66,79,85	
20 DATA 52,66,80,79,98,95,89,68,72,96	
30 DIN AC1003	
40 MAT A=ZER	
50 FOR I=1 10 20	
88 NEXT I	
90 PRINT "GRADE: NUMBER OF STUDENTS"	
100 FOR T=1 TO 100	
110 IF ALT=0 THEN 130	
120 PRUNT LAREL	
130 NEXT 1	

4-14



Syntax:

MAT matrix name = IDN [expression , expression]

An identity matrix is a square matrix containing zeros with a principal diagonal containing all ones.

The statement MAT B=IDN(3,3) results in the following 3 by 3 matrix:

1	0	0
0	1	0
0	0	1

If no subscripts are given, the identity matrix has the most recent dimensions specified. If subscripts are given, they must be equal, and they cause the array to be dimensioned to the specified size:

			网络黑龙龙王尼斯美国西西美国西部城市西部国际西部城市地区的东西市 化合金	
4,000 (4.4.00.000	1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1		and the second and the second and a second and the second s	
10 1161	AHIDN		"你们,你们还是你的,你,你不能能要要吃饭,你们还是你了。"	
and the second	m. www.iire.em		and the second and second and the second s	
20 MM I	BELUNLD	5 3 1	マン・ション・ションス ひゃう ゆうちゅう かんしょう しゅうしょう しょうしょう	
ISM MHI	X=IDNDQ	4 d d - 1	- こ かっ ひょう しゅう ちゃ ちゃ デオ デオ アイン アイア ちゃく カート やく ちょう	
	it is an any fifth out	1. 1011 M	·····································	and the second

The identity matrix is defined as the matrix which, when multiplied by any Matrix A results in Matrix A. It is used by mathematicians in fields such as numerical analysis in determining the accuracy of inversions.

Syntax:

MAT matrix name = INV (matrix name)

The inverse of a Matrix A is a Matrix B which, when multiplied by the original Matrix A, produces the identity matrix. Both Matrix A and B should be full precision matrices to insure accuracy. Only a square matrix can be inverted:

110 MAT H=INV(B) 120 MAT X=INV(X)

The same matrix may appear on both sides of the equals sign, as in statement 120, above.

In performing the inversion, the calculator must generate an additional internal work area. For an N by N matrix, the additional amount of internal work area required is N words of calculator memory.

Inversions can be used to help solve sets of simultaneous linear equations. Here is a word problem which is solved by using simultaneous linear equations:

John bought 3 oranges and 4 apples for 47 cents, and Mary bought 2 oranges and 2 apples for 28 cents. How much is 1 orange? How much is 1 apple?

We set up the following equations from the problem:

$$3X + 4Y = 47$$

 $2X + 2Y = 28$

Using the values of the coefficients on the left side of the equations in Matrix A, we have the following 2 by 2 matrix:

3 4 2 2 Computer Museum

Using the values of the constants on the right side of the equations in Matrix B, we have the following 2 by 1 matrix:

47 28

To find the values for X and Y, we use the matrix inversion command and a matrix multiplication:

	$ \begin{array}{c} 1 \neq j = -j + -j = j + -j + j + -j + -j + -j$	· 医弗莱克 · · · · · · · · · · · · · · · · · · ·
	· · · · · · · · · · · · · · · · · · ·	방법 동안은 승규야 같이 있는 것은 것을 수 있었다. 방문 가슴 말했는 것을 가지 않는 것을 수 있었다.
The second s	""""""""""""""""""""""""""""""""""""""	
3. 46. C.2. 28, 402		
21 Mathematical South State Sta State State S		
이는 것 같아요. 이는 것 같아요. 한 것 같아요. 이는 것은 것이는 것은 것 같아요. 한 것 같아요. 이는 것	""""""""""""""""""""""""""""""""""""""	こうてき アイト・トリア・タイム しんしょう しきがく オート・アイト しょうしょう しょうしょう たいさい しょうしん
a series for the second s	人名德尔 医马克尔 化分离子 医多子子 医鼻子 医鼻子 医鼻子 医外外的 计算法 化分子 化分子 化分子 化分子	요즘 이 것은 상태에서 제공을 가지 않는 것 같은 것에서 가지 않는 것이 있는 것이 없는 것이 있는 것이 없다.
[1] Kin Wilson, Kin Kull, "Proceeding Control Kall, Mathematical Systems, and and an approximately statement of the system of		医鼻腔炎 化乙酸乙酸乙酸乙酸乙酸乙酯 化分子 法法律法 法法律法 化乙烯基苯乙烯 法法律保证 化乙烯基苯乙酸
CONTRACTOR STATEMENTS AND A STATEMENTS AND	化氯化化物 医结核 医结核 化化合物 化化合物 化化合物 化合物 化合物 化合物 化合物 化合物 化合物	2.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1
[1] Suff Suffer and J. U. E. Press, Suffering E. U. Stational and Active Sciences.	第二 "你是,我也是想到你是你的是你的是你,你们还不知道你的?你不是你的?" 医外外外的 医生子子的	
	For E-SISH Sector - Viller	우리는 일정 방향한 동생은 것을 수많다. 승규는 유민이는 지난 문화되는 것만 하는 것
50 MAT C=A★B	"你们是你,你们还能要不能你,你们还是你的你,你们你?""你们,你们你不知道,你们你不知道你?"	그는 사람이 잘 잘 많은 것이 같아요. 이 같은 것은 것을 가지 않는 것이 많이 많이 있는 것을 했다.

Now the price of an orange, X, is contained in C(1,1), and the price of an apple, Y, is contained in C(2,1).

Here are the program instructions to perform the matrix inversion and print the result.

10 DIM AC2;2],BC2;1],CC2;1]
20 MAT READ A;B
30 DATA 3;4;2;2;47;28
40 MAT A=INV(A)
50 MAT C=A*B
60 FORMAT F4.0; " CENTS EACH";/;F4.0; " CENTS EACH"
70 WRITE (15;60)"APPLES ";CC1;1]; "ORANGES";CC2;1]

Even though a matrix is square, it may not have an inverse. A calculator error will occur when an inversion is attempted and the matrix has no inverse. Therefore, it is sometimes useful to insure that the matrix has an inverse by making sure that its determinant is not equal to zero. More discussion of the determinant follows.

For a more detailed explanation of matrix inversion, you can refer to an advanced mathematics textbook.

+++++ DETERMINANTS +++++

Syntax:


DET (matrix name)

The DET function calculates the determinant of a square matrix:

10 X=DET(H) 20 Y=X+DET(H)

A determinant is a measure of the independence of the rows (or columns) of a matrix. The DET function returns a numerical value to an expression. For an N by N matrix, the additional amount of internal work area required is equal to the original size of the matrix plus N words. The matrix for which a determinant is evaluated should be full precision to insure accuracy.

If the determinant of a square matrix of simultaneous linear equations is not zero, the system of equations has precisely one solution; that is, the inverse of the matrix can be obtained. On the other hand, if the determinant is zero, the system of equations has no precise solution, and the matrix has no inverse. Therefore, it may be useful to use the DET function to examine the matrix before inversion is performed in order to prevent a calculator error condition. Following is an example:



A linear relationship exists between the daily temperature and a vending machine company's sale of soft drinks. The company wishes to be able to predict sales based on daily temperatures. This example shows how the company might do this by performing a regression analysis using the statistical method known as least squares fit.

Table 4-1 contains some of the sales figures and daily maximum temperatures.

Table 4-1. Sales Figures vs. Maximum Daily Temperatures

Maximum Temperature	Sales (\$)
81	41
64	30
57	26
76	36
92	49

The company performs a simple linear regression to find the relationship between temperatures and sales. If this is done by hand, first a computation table like Table 4-2 is needed, where X values are temperatures, and Y values are sales.

X	Y	X*Y	X ²
81	41	3321	6561
64	30	1920	4096
57	26	1482	3249
76	36	2736	5776
92	49	4508	8464
370	182	13967	28146

Table 4-2. Computation Table for Regression

The value of sales (Y) can be predicted for any temperature (X) by using the formula Y=A+BX. But first the values of A and B must be calculated. To find A and B, the following two simultaneous equations are solved:

$$An+B\Sigma X=\Sigma Y$$
$$A\Sigma X+B\Sigma X^{2}=\Sigma X Y$$

Where n is the number of entries, in this case five.*

From the computation table, we know the following values:

 Σ X=370; Σ Y=182; Σ XY=13967 and Σ X²=28146.

Now the two equations are

| 5A+370B=182 || 370A+28146B=13967

To solve the simultaneous equations by hand, we eliminate A from the equations by multiplying the first equation by 370 and the second by 5 and then subtracting Equation I from Equation II.


II 1850A+140730B=69835 I 1850A+136900B=67340 3830B=2495

B=2495/3830B=.6514

Although it would be easy by the method of substitution to find the value of A, now that the value of B is known, the value of A is of little significance in this case. However, the regression coefficient, B, is of interest: it represents an estimate of the average increase in sales for each additional degree of temperature. That is, within the temperatures studied, each additional degree in temperature increases sales by an average of 0.65 dollars.

The above procedure is repeated in the program steps which follow. First, Matrix A is set up, containing the X, Y, XY, and X² values shown in the computation table. The summation (Σ) values are then calculated and stored in Matrix C: C(1,1)= Σ X; C(2,1)= Σ Y; C(3,1)= Σ XY; and C(4,1)= Σ X².

^{*} Increasing the number of entries in the computation table results in a more accurate prediction; however, for purposes of explanation, five entries are sufficient.



To solve for A and B, we must perform a matrix inversion on the coefficients of the following simultaneous equations:

5A+C(1,1)B=C(2,1) C(1,1)A+C(4,1)B=C(3,1)

The coefficients on the left of the equals sign are contained in Matrix M, and those on the right are in Matrix N.

Matrix M	5	C(1,1)	Matrix N	C(2,1)
	C(1,1)	C(4,1)		C(3,1)

The following instructions create Matrix M and Matrix N, and perform the necessary inversion and multiplication so that Matrix P contains the value of A, in P(1,1), and B, in P(2,1).

130 DIM ME2,21,NE2,11,PE2,11 140 ME1,1]=5	
- 1997年19月1日 - 19月1日 - 19月	
a La La Martin Carlon Carlon La Carlon Carlon a Construction of the Construction of th	
- * * 2. 21、* 1944 との記録「21、1955年1944」(1953年) * * * * * * * * * * * * * * * * * * *	
200 MET H=LHV(H)	
215 FIXED 2 220 PRINT "THE REGRESSION COEFFICIENT IS ";PC2,I]	
「「「」、「「「「「「「」」」」」「「「」」」」「「」」」」「「」」」」」「「」」」」」」	

APPENDIX

INDICATI	ON	MEANING	
ERROR	66	Matrix must be square for attempted operation.	
ERROR	67	New dimensions exceed existing DIM specifications.	
ERROR	68	Matrix has no inverse. The data contained in the matrix does not have a solution.	
ERROR	69	Incompatible dimensions. Dimensions of added, subtracted, multiplied, copied or transposed matrices must agree.	



WORLD WIDE **SALES & SERVICE OFFICES**

UNITED STATES

ALABAMA 8290 Whitesburg Dr., S.E. P.O. Box 4207 Huntsville 35802 Tel: (205) 881-4591 TWX: 810-726-2204 *Birmingham Medical Service only Tel: (205) 879-2081 ARIZONA 2336 E. Magnolia St. Phoenix 85034 Tel: (602) 244-1367 TWX: 910-951-1331

CALIFORNIA 1430 East Orangethorpe Ave. Fullerton 92631 Fullerton 92631 Tel: (714) 870-1000 TWX: 910-592-1288 3939 Lankershim Boulevard North Hollywood 91604 Tel: (213) 877-1282 TWX: 910-499-2170 6305 Arizona Place Los Angeles 90045 Tel: (213) 649-2511 TWX: 910-328-6147 Los Angeles Tel: (213) 776-7500 3003 Scolt Boulevard Santa Clara 95050 Tel: (408) 249-7000 TWX: 910-338-0518 **Ridgecrest** Tel: (714) 446-6165

2220 Watt Ave. Sacramento 95825 Tel: (916) 482-1463 TWX: 910-367-2092 9606 Aero Drive P.O. Box 23333 San Diego 92123 Tel: (714) 279-3200 TWX: 910-335-2000

2424 East Aragon Rd. Tucson 85706 Tel: (602) 889-4661

COLORADO 5600 South Ulster Parkway Englewood 80110 Tel: (303) 771-3455 TWX: 910-935-0705 CONNECTICUT 12 Lunar Drive New Haven 06525 Tel: (203) 389-6551 TWX: 710-465-2029 FLORIDA FLORIDA P.O. Box 24210 2806 W. Oakland Park Bivd. Ft. Lauderdale 33307 Tel: (305) 731-2020 TWX: 510-955-4099 *Jacksonville Medical Service only Tel: (904) 725-6333 P.O. Box 13910 6177 Lake Ellenor Or. Orlando 32809 Tel: (305) 859-2900 TWX: 810-850-0113 21 East Wright St. Suite 1 Pensacola 32501 Tel: (904) 434-308 GEORGIA P.O. Box 28234 450 Interstate North Atlanta 30328 Tei: (404) 434-4000 TWX: 810-766-4890 HAWAII 2875 So. King Street Honolulu 96814 Tel: (808) 955-4455 ILLINOIS (Calculators Only) 100 S. Wacker Drive Suite 1100 Chicago 60606 Tel: (312) 346-9701

5500 Howard Street Skokie 60076 Tel: (312) 677-0400 TWX: 910-223-3613

*St. Joseph Tel: (217) 469-2133

INDIANA 3839 Meadows Drive Indianapolis 46205 Tel: (317) 546-4891 TWX: 810-341-3263 IOWA 1902 Broadway Iowa City 52240 Tel: (319) 338-9466 Night: (319) 338-9467 *KANSAS Derby Tel: (316) 267-3655 LOUISIANA P.O. Box 840 3239 Williams Boulevard Kenner 70062 Tel: (504) 721-6201 TWX: 810-955-5524 MARYLAND MARYLAND 6707 Whitestone Road Baltimore 21207 Tel: (301) 944-5400 TWX: 710-862-9157 4 Choke Cherry Road Rockville 20850 Tel: (301) 948-6370 TWX: 710-828-9685 710-828-0487 P.O. Box 1648 2 Choke Cherry Road **Rockville** 20850 Tel: (301) 948-6370 TWX: 710-828-9684 MASSACHUSETTS

32 Hartwell Ave. Lexington 02173 Tel: (617) 861-8960 TWX: 710-326-6904 MICHIGAN MICHIGAN 23855 Research Drive Farmington 48024 Tel: (313) 476-6400 TWX: 810-242-2900

MINNESOTA 2400 N. Prior Ave. Roseville 55113 Tel: (612) 636-0700 TWX: 910-563-3734

MISSISSIPPI *Jackson Medical Service only Tel: (601) 982-9363

MISSOURI MISSOORI 11131 Colorado Ave. Kansas City 64137 Tel: (816) 763-8000 TWX: 910-771-2087 148 Weldon Parkway Maryland Heights 63043 Tel: (314) 567-1455 TWX: 910-764-0830 NEBRASKA (Medical Dniy) 11902 Elm Street Suite 4C Omaha 68144 Tel: (402) 333-6017 NEVADA Las Vegas Tel: (702) 382-5777 NEW JERSEY W. 120 Century Rd. Paramus 07652 Tel: (201) 265-5000 TWX: 710-990-4951 NEW MEXICO P.O. BOx 8366

Station C 6501 Lomas Boulevard N.E. Albuquerque 87108 Tel: (505) 265-3713 TWX: 910-989-1665 156 Wyatt Orive Las Cruces 88001 Tel: (505) 526-2485 TWX: 910-983-0550

NEW YORK 6 Automation Lane Computer Park Albany 12205 Tel: (518) 458-1550 TWX: 710-441-8270 TWK: 710-441-8270 New York City Manhaitan, Bronx Contact Paramus, NJ Office Tel: (201) 265-5000 Brookiyn, Queens, Richmond Contact Woodbury, NY Office Tel: (516) 921-0300 201 South Avenue **Poughkeepsie** 12601 Tel: (314) 45-7300 TWK: 510-248-0012 39 Saninay Drive 39 Saginaw Drive Rochester 14623 Tel: (716) 473-9500 TWX: 510-253-5981 5858 East Molloy Road Syracuse 13211 Tel: (315) 455-2486 TWX: 710-541-0482 1 Crossways Park West Woodbury 11797 Tel: (516) 921-0300 TWX: 510-221-2168 NORTH CAROLINA P.O. Box 5188 1923 North Main Street High Point 27262 Tel: (919) 885-8101 TWX: 510-926-1516 OHIO 16500 Sprague Road Cleveland 44130 Tel: (216) 243-7300 Night: 243-7305 TWX: 810-423-9431 330 Progress Rd. Dayton 45449 Tel (513) 859-8202 TWX: 810-459-1925 1041 Kingsmill Parkway Columbus 43229 Tel: (614) 436-1041

OKLAHOMA P. 0. Box 32008 Oklahoma City 73132 Tel: (405) 721-0200 TWX: 910-830-6862 OREGON 17890 SW Boones Ferry Road Tualatin 97062 Tel: (503) 620-3350 TWX: 910-467-8714 PENNSYLVANIA 111 Zeta Drive Pittsburgh 15238 Tel: (412) 782-0400 Night: 782-0401 TWX: 710-795-3124 1021 8th Avenue King of Prussia Industrial Park King of Prussia 19406 Tel: (215) 265-7000 TWX: 510-660-2670 SOUTH CAROLINA 6941-0 N. Trenholm R Columbia 29260 Tel: (803) 782-6493 Road TENNESSEE *Memphis Medical Service only Tel: (901) 274-7472 *Nashville Medical Service only Tel: (615) 244-5448 TEXAS P.O. Box 1270 201 E. Arapaho Rd. Richardson 75080 Tel: (214) 231-6101 TWX: 910-867-4723 P.O. Box 27409 6300 Westpark Orive Suite 100 Houston 77027 Tel: (713) 781-6000 TWX: 910-881-2645

205 Billy Mitchell Road San Antonio 78226 Tel: (512) 434-8241 TWX: 910-871-1170

UTAH 2890 South Main Street Sait Lake City 84115 Tel: (801) 487-0715 TWX: 910-925-5681 VIRGINIA

*Norfolk Medical Service only Tel: (804) 497-1026 P.O. Box 9854 2914 Hungary Springs Road **Richmond** 23228 Tel: (804) 285-3431 TWX: 710-956-0157

WASHINGTON Bellefield Office Pk WASHINGTON Beliefield Office Pk. 1203-114th SE Believue 98004 Tel: (206) 454-3971 TWX: 910-443-2446

WEST VIRGINIA Charleston Tel: (304) 345-1640

WISCONSIN 9431 W. Beloit Road Suite 117 Milwaukee 53227 Tel: (414) 541-0550

FOR U.S. AREAS NOT LISTED: Contact the regional office nearest you. Allanta, Georgia... North Hollywood, California... Rockville, 4 Choke Cherry Rd.) Maryland...Skokie. Illinois. Their complete addresses are listed above.

Service Only

CANADA

ALBERTA Hewiett-Packard (Canada) Ltd. 11748 Kingsway Ave. Edmonton TSG 0X5 Tel: (403) 452-3670 TWX: 610-831-2431 Hewlett-Packard (Canada) Ltd. 915-42 Avenue S.E. Suite 102 Calgary T2G 121 Tel: (403) 287-1672

ARGENTINA Hewlett-Packard Argentina S.A.C.e.I Lavalle 1171-3" Piso Buenos Aires Tel: 35-0436, 35-0627, 35-0341 Telex: 012-1009 Cable: HEWPACK ARG

Gable: REVEAUX AND BOLIVIA Stambuk & Mark (Bolivia) Ltda. Av. Mariscal, Santa Cruz 1342 La Paz Tel: 40626, 53163, 52421 Telex: 3560014 Cable: BUKMAR

BRAZIL Hewlett-Packard Oo Brasil I.E.C. Ltda Rua Frei Caneca. 1. 152-Bela Vista 01307-São Paulo-SP Teir 288-71-11, 287-81-20, 287-61-93 Talar 2001 12/212

BRITISH COLUMBIA Hewiett-Packard (Canada) Ltd. 837 E. Cordova Street Vancouver V6A 3R2 Tel: (604) 254-0531 TWX: 610-922-5059

MANITOBA Hewlett-Packard (Canada) Ltd. 513 Century SI. St. James Winnipeg R3H 0L8 Tel: (204) 786-7581 TWX: 610-671-3531

NOVA SCOTIA Hewlett-Packard (Canada) Ltd. 800 Windmill Road Dartmouth B3C 1L1 Tel: (902) 469-7820 TWX: 610-562-8968 Hewlett-Packard (Canada) Ltd. 6877 Goreway Drive **Mississauga** L4V 1L9 Tel: (416) 678-9430 TWX: 610-492-4246

PERU Compañia Electro Médica S.A. Ave. Enrique Canaual 312 San Isidro Casilla 1030 Lima Tel: 22-3900 Cable: ELMED Lima Cable: ELMED Lima **PUERTO RICO** San Juan Electronics, Inc. P.O. Box 5167 Ponce de León 154 Ponce de León 154 Pda. 3-PTA de Tierra San Juan 00906 Tel: (809) 725-3342, 722-3342 Cable: SATRONISS San Juan Telex: SATRON 3450 332

OUEBEC Hewlett-Packard (Canada) Ltd. 275 Hymus Blvd. Pointe Claire H9R 167 Tel: (514) 697-4223 TWX: 610-422:3022 TLX: 05-821521 HPCL

Montevideo Tel: 40-3102 Cable: RADIUM Montevideo

Hewlett-Packard (Canada) Ltd. 2376 Galvani Street **Ste-Foy** G1N 4G4 Tel: (418) 688-8710

FOR CANADIAN AREAS NOT LISTED: Contact Hewlett-Packard (Canada) Ltd. in Mississauga.

VENEZUELA Hewlett-Packard de Venezuela

Hewlett-Packard de Venezu C A. Apartado 50933 Edificio Segre Tercera Transversal Los Ruices Norte **Caracas** 107 Tel: 35-00-11 Telex: 21146 HEWPACK Cable: HEWPACK Caracas

FOR AREAS NOT LISTED, CONTACT: Hewlett-Packard Inter-Americas 3200 Hillview Ave. Palo Alto, California 94304 Tel: (415) 493-1501 TWX: 910-373-1260 Cable: HEWPACK Palo Alto Telex: 034-8300, 034-8493

EUROPE

Telex: 309151/2/3 Cable: HEWPACK São Paulo

AUSTRIA AUSTRIA Hewlett-Packard Ges.m.b.H. Handeiska 52:3 P.O. Box 7 A:1205 Vienna Tel: (0222) 33 66 06 to 09 Cable: HEWPAK Vienna Telex. 75923 hewpak a Hewlett-Packard Oo Brasil I.E.C. Ltda. Praca Dom Feliciano. 78-8° andar (Sala 806/8) 9000-Porto Alegre-RS Tei: 25-84-70-DDD (0512) Cable: HEWPACK Porto Alegre Cable: HEWPACK Pórto Alegre Hewlett-Packard Oo Brasil I E.C. Lida. Rua Sigueira Campos. 53, 4° andar Copacabana 2000-Rio de Janeiro-GB Tel: 257-80-94-DD0 (021) Telex. 2100 79 HEWPACK Cable: HEWPACK Rio de Janeiro GUATEMALA CHILE GUATEMALA IPESA Avenida La Reforma 3-48. Zona 9 Guatemala Tel: 63627, 64736 Telex: 4192 TELTRO GU CHILE Calcagni y Metcalfe Lida. Calle Lira 81. Oficina 5 Casilla 2118 Santiago Tel: 398613 Cable: CALMET

BELGIUM Hewlett-Packard Benelux S A: N. V. Avenue de Col-Vert. 1. (Groenkraagiaan) B-1170 Brussels Tel: (02) 672 22 40 Cable: PALOBEN Brussels Telex. 23 494 paloben bru

CENTRAL AND SOUTH AMERICA MEXICO Hewiett-Packard Mexicana. S.A. de C.V. Torres Adalid No. 21, 11° Piso Col. del Valle Mexico 12, 0.F. Tel: (905) 543-42-32 Telex: 017.74-507 COLOMBIA CollometA Instrumentación Henrik A. Langebaek & Kier S.A. Carrera 7 No. 48-59 Apartado Aéren 6287 Bogota, 1 D.E. Tel 45-78-06, 45-55-46 Cabie: AARIS Bogota Telex: 44400INSTCO COSTA RICA COSTA RICA Lic. Alfredo Gallegos Gurdián Apartado 10159 San José Tel: 21-86-13 Cabie: GALGUR San José

DENMARK Hewlett-Packard A/S Datavej 52 DK-3450 Birkerød

Tel: (01) 81 66 40 Cable: HEWPACK AS Telex: 166 40 hp as

Hewlett-Packard Mexicana. S.A. de C.V. Ave. Constitución No. 2184 Monterrey, N.L. Tel: 48-71-32, 48-71-84 NICARAGUA Roberto Terán G. Apartado Postal 689 Edificio Terán Managua Tel: 3451, 3452 Cable: ROTERAN Managua

PANAMA Electrónico Balboa, S.A. P.O. Box 4929 Calle Samuel Lewis Cuidad de Panama Tei: 64-2700 Telex: 3431103 Curunda, Canal Zone Cable: ELECTRON Panama PARAGUAY Z.J. Melamed S.R.L. Division: Aparatos y Equipos Medicos Division: Aparatos y Equipos Scientíficos y de Scientificos y de Investigación P.O. Box 676 Chile, 482, Edificio Victoria Asunción Tel: 4-5069, 4-6272 Cable: RAMEL

URUGUAY Pablo Ferrando S.A. Comercial e Industrial Avenida Italia 2877 Casilla de Correo 370

FRANCE

FRANCE Hewlett-Packard France Ouartier de Courtaboeuf 8oite Postale No. 6 F-91401 Orsay Tel: (1) 907 78 25 Cable: HEWPACK Orsay Telex: 60048

Hewlett-Packard France Hewlett-Packard Franc Agence Régional Chemin des Mouilles Borte Postale No. 12 F-69130 Ecully Tel: (78) 33 81 25. 83 65 25 Telex: 31 617

Hewlett-Packard A:S Navervej 1 DK-8500 **Silkeborg** Tel: (06) 82 71 66 Telex: 166 40 hp as Cable: HEWPACK AS

FINLAND Hewlett-Packard Oy Nahkahousuntie 5 P 0 Box 6 SF-00211 Helsinki 21 Tel: 6923031 Cable: HEWPACKOY Helsinki Telex: 12-15363

ONTARIO Hewieti-Packard (Canada) Ltd. 1785 Woodward Or. Ottawa K2C OP9 Tel: (613) 225-6530 TWX: 610-562-8968

Hewlett-Packard France Agence Regionale Zone Aéronautique Avenue Clément Ader F-31770 Colomiers Tel: (611,78 11 55 Telex: 51957 Hewelti-Packard France Agence Régionale Centre d'aviation générale F-13721 Aéroport de Marignane Tel: (91) 89 12 36 TWX 41770 F Hewietl-Packard France Agence Régionale 63. Avenue de Rochester F-35000 **Rennes** Tel: 74912 F Telex. 74 912 F Telex: 74 912 F Hewlett-Packard France Agence Regionate 74. Allée de la Robertsau F-67000 Strasbourg Tel (88) 35 23 20 21 Telex: 89141 Cable: HEWPACK STRBG GERMAN FEDERAL REPUBLIC

Hewlett-Packard GmbH Vertriebszentrale Frankfurt Bernerstrasse 117 Posttach 560 140 D-6000 Frankfurt 56 Tel: (0611) 50 04-1 Cable: HEWPACKSA Frankfurt Telex: 41 32 49 fra Telex 41 52 49 fra Hewlett-Packard GmbH Vertriebsburo Boblingen Herrenbergerstrasse 110 D-7/303 **Gbblingen**, Wurttemberg Tel. (07031) 66 72 87 Cable: HEPAK Boblingen Telex: 72 65 739 bbn

Hewiett-Packard GmbH Vertriebsbüro Düsseldorf Vogelsanger Weg 38 D-4000 **Düsseldorf** Tel: (0211) 63 80 31 5 Telex. 85:86 533 hpdd d Telex, 85:85 533 hpdd d Hewlett-Packard GmbH Vertriebsburo Hamburg Wendenstrasse 23 0-2000 Hamburg 1 Tel: (040) 24 13 93 Cable: HEWPACKSA Hamburg Telex, 21 63 032 hphh d Hewlett Packard 0-bit Hewlett-Packard GmbH Vertriebsburo Hannover Mellendorter Strasse 3 0-3000 Hannover-Kle Tel: (0511) 55 60 46 Telex: 092 3259 Hewiet 092 3259 Hewiett-Packard GmbH Vertriebsbüro Nuremberg Hersbrückerstrasse 42 D-8500 Nuremberg Tel. (0911) 57 10 66 Telex. 623 860 Hewlett-Packard GmbH Vertrebsburr Munchen Unterhachinger Strasse 28 ISAR Center D-8012 Ottobrunn Tel (089) 601 30 61/7 Telex: 52 49 85 Cable: HEWPACKSA Munchen (West Berlin) (West Berlin) Hewiett-Packard GmbH Vertriebsbüro Berlin Keith Strasse 2-4 D-1000 Berlin 30 Tel: (030) 24 90 86 Telex: 18 34 05 hpbln d

GREECE Kostas Karayannis 18. Ermou Street GR-Athens 126 Tel 3230-305 Sales/SVC 3230-305 Adm. Order Proc. Cable RAKAR Athens Teirx 21 59 52 rkar gr Hewlett-Drevel 5. 6 Telex 21 59 62 rkar gr Hewlett-Packard S.A. Mediterranean & Middle East Operations 35 Kolokotroni Street Plata Kefallariou Gr-Killssia-Athens Tel: 8080337, 8080359, 8080429, 8018693 Telex: 21 6588 Cable: HEWPACKSA Athens IRELAND Hewlett-Packard Ltd. King Street Lane Winnersh, Workingham GB-Berkshire RG11 5AR Tel: Wokingham 764774 Telex: 847178/848179 Hewlett-Packard Ltd. Telex: 847178/848179 Hewlett-Packard Lld. "The Grattons" Stamford New Road GB-Altrincham, Cheshire Tel: (061) 928-9021 Telex: 668068 Have tooloo ITALY Hewlett-Packard Italiana S.p.A. Via Amerigo Vespucci 2 I-20124 Milan Tel. (2) 6251 (10 lines) Cable: HEWPACKIT Milan Telex: 32046 Telex: 32046 Hewlett-Packard Italiana S.p.A. Via Pietro Maroncelli 40 (ang. Via Visentin) I-35100 Padowa Tel: 66 40 62/66 31 88 Telex: 32046 via Milan

Hewlett-Packard Italiana S.p. A. Via Medaglie d'Oro, 2 1-55100 Plas Telex, 32045 va Millan Hewlett-Packard S.p. A Via G. Armellini 10 1-00143 **Arme**-Eur Tel: (6) 5912544/5 Telex: 6151 Cable: HEWPACKIT Rome Hewlett-Packard Italiana S.p. A Hewlett-Packard Italiana S.p.A. Via San Ouintino, 46 I-10121 Turin Tei: (11) 53 82 64 Telex: 32046 via Milan LUXEMBURG Hewiett-Packard Benelux S.A./N.V. Avenue de Col-Vert, 1, (Groenkraaglaan) B-1170 Brussels Tel: (02) 672 22 40 Cable: PALOBEN Brussels Telex: 23 494 NETHERLANDS Hewiett-Packard Bei Weerdestein 117 P.O. Box 7825 Benelux N V PLC: B0X 7825 NL-**Amsterdam**, 1011 Tel: (020) 5411522 Cable: PALOBEN Amsterdam Telex: 13 216 hepa nl NORWAY NORWAY Hewlett-Packard Norge A/S Nesveien 13 Box 149 N-1344 Haslum Tel: (02) 53 83 60 Telex: 16621 hpnas n

PORTUGAL Telectra-Empresa Técnica de Equipamentos Eléctricos S a.r.1 Rua Rodrígo da Fonseca 103 P O. Box 2531 P-Lisbon T Tel. (19) 68 60 72 Cable: FELECTRA Lisbon Telex. 12598 Tetex: 12598 SPAIN Hewlett-Packard Española. S.A. Jerez No. 3 E-Madrid 16 Tel: 458 26 00 Telex: 22515 hpe Hewlett-Packard Española, S.A. Milanesado 21-23 E-Barcetono 17 Tel: (3) 2036200-08, 2044098/9 Telex: 52603 hpbe e Hewlett-Packard Española, S.A. Hewiett-Packard Española, S.A. Av Ramon y Cajal, 1 Edificio Sevilla I, planta 9° E-**Seville** Tel: 64 44 54/58 Hewlett-Packard Española S.A. Edificio Albia H 7° 8 E-Bilbao Tel: 23 83 06/23 82 06 SWEDEN SWEDEN Hewlett-Packard Sverige AB Enighetsvägen 1-3 Fack S-161 20 Bromma 20 Tel: (08) 730 05 50 Cable: MEASUREMENTS Stockholm Telex: 10721 Hewlett-Packard Sverige AB Hagakersgatan 9C S-431 41 **MoIndai** Tel: (031) 27 68 00/01 Telex: Via Bromma

SWITZERLAND Hewlett-Packard (Schweiz) AG Zürcherstrasse 20 P. Box 54 CH-8952 Schlieren Zurich Tei: (01) 98 18 21 Cable: HPAG CH Telex: 53933 hpag Heiki: 53933 npag Hewlett-Packard (Schweiz) AG 9. chemin Louis-Pictet CH-1214 Vernier- Geneva Tel: (022) 41 49 50 Cable: HEWPACKSA Geneva Telex: 27 333 hpsa ch TURKEY TURKEY Telekom Engineering Bureau Saglik Sok No. 15/1 Ayaspasa-Beyoglu P.O. Box 437 Beyoglu TR-Istanbul Tel: 49 40 40 Cable: TELEMATION Istanbul UNITED KINGDOM UNITED KINGDOM Hewlett-Packard Ltd. King Street Lane Winnersh. Wokingham GB-Berkshire RG11 5AR Tel: Workingham 784774 Telex: 847178/848179 Hewielt-Packard Ltd. "The Graftons" Stamford New Road GB-Altrincham, Cheshire Tel: (061) 928-9021 Telex: 668068 reiex: bb8068 Hewlett-Packard Ltd. c'o Makro South Service Wholesale Centre Amber Way Halesowen Industrial Estate **G8-Halesowen**, Worcs Tel: Birmingham 7860

Hewlett-Packard Ltd 4th Floor Wedge House 799. London Road GB-Thornton Heath CR4 6XL Surrey Tel: (01) 684 0105 Telex: 946825 Hewlett-Packard Ltd. Cio Makro South Service Wholesale Centre Wear Industrial Estate Washingtonal Washington GB-**New Town**. County Durham Tel: Washington 464001 ext. 57/58 Hewlett-Packard Ltd.'s registered address for V.A.T. purposes only: 70, Finsbury Pavement London, EC2A1SX Registered No. 690597 Registered No. 690597 USSR Hewlett-Packard Representative Office USSR Hotel Budapest/Room 201 Petrovskie Linii 2/18 Moscow Tet: 221-79-71 YUGOSLAVIA Iskra-Standard/Hewiett-Packard Topniska 58/3 61000 Ljubljana Tel: 314561 or 314927 Telex: 31300 Telex: 31300 SOCIALIST COUNTRIES PLEASE CONTACT: Hewlett-Packard S.A. 7. rue du Bois-du-Lan P. 0. Box 34 CH: 1217 Meyrin 1 Geneva Switzerland Tel: (022) 41 54 00 Cable: HEWPACKA Geneva Telex: 2 24 86

AFRICA, ASIA, AUSTRALIA

ANGOLA

Telectra Empresa Técnica de Equipamentos Equipamentos Eléctricos, S.A.R.L. R. Barbosa Rodrigues, 42-1"DT.º Caixa Postal, 6487-Luanda Tel: 35515/6 Cable: TELECTRA Luanda AUSTRALIA Hewlett-Packard Australia Hewlett-Packard Australia Pty. Ltd. 31-41. Joseph Street Blackburn, Victoria 3130 Tel: 89-6351, 89-6306 Telex: 31-024 Cable: HEWPARO Melbourne Hewlett-Packard Australia Pty. Ltd. 31 Bridge Street Pymble. New South Wales. 2073 Tel: 449-6566 Telex: 21561 Cable: HEWPARD Sydney Hewlett-Packard Australia Pty. Ltd. 97 Churchill Road 97 Churchin Hoad Prospect 5082 South Australia Tel: 44 8151 Cable: HEWPARD Adelaide Hewlett-Packard Australia Pty. Ltd. 141 Stirling Highway Neclands, W A., 6009 Tel: 86 5455 Hewlett-Packard Australia Pty Ltd. 121 Wollongong Street Fyshwick, A.C.T., 2609 Tel: 95 3733

Ter 95 3733 Hewlett-Packard Australia Pty Ltd 5th Floor Teachers Union Building 495-499 Boundary Street Spring Hill, 4000 Queensland Tel: 29-1544 Telex: AA-42133 CEYLON United Electricals LId P.O. Box 681 60. Park St.

Colombo 2 Tel: 26696 Cable HOTPO HOTPOINT Colombo

CYPRUS Kypronics 19 Gregorios & Xenopoulos Rd. P O Box 1152 CY-Nicosia Teil 45628/29 Gable: KYPRONICS PANDEHIS Cable: AFPRONICS PANDE ETHIOPIA African Salespower & Ager Private Ltd., Co. P.O. Box 718 58/59 Cunningham St. Addis Ababa Tel: 12285 Cable: ASACD Addisababa ower & Agency , Co. Lable AsACD Addisababa HONG KONG Sottmid & Co. (Hong Kong) Lid. P. Box 27 Connsight Centre 39th Floor Connsight Road. Central Hong Kong Tel: 240158. 232735 Telex. NAX762 Cable: SCHMIDTCO Hong Kong INDIA Biue Star Ltd. Kasturi Buildings Jamshedji Tata Rd. Bombay 400 020 Tel: 29 50 21 Telex: 3751 Cable: BLUEFROST Bius Star Ltd. Blue Star Ltd. Sahas 414/2 Vir Savarkar Marg rabhan Prabhadevi Bombay 400 025 Tel: 45 78 87 Telex: 4093 Cable: FROSTBLUE Cable: FROSTBLUE Blue Star Ltd. Band Box House Prabhadevi Bombay 400 025 Tel: 45 73 01 Telex: 3751 Cable: BLUESTAR Blue Star Ltd. 14/40 Civil Lines Kampur 208 001 Tel: 6 88 82 Cable: BLUESTAR Blue Star Ltd 7 Hare Street P 0. Box 506 Calcutta 700 001 Tel: 23-0131 Telex: 655 Cable: BLUESTAR

Blue Star Ltd. Blue Star House. 34 Ring Road Laipat Nagar New Dethi 110 024 Tel: 62 32 76 Tetex: 2463 Cable: BLUESTAR Blue Structure Cable: BLDESTAR Blue Star Ltd. Blue Star House 11/11A Magarath Road Bangaiore 560 025 Telex: 430 Cable: BLUESTAR Blue Star Ltd. Meeakshi Mandiran xxx/1678 Mahatma Gandhi Rd. Cochin 682 016 Kerala Blue Star Ltd. 1-1-117/1 Sarojini Oevi Road Secunderabad 500 003 Tel: 7 63 91, 7 73 93 Cable: BLUEFROST Telex: 459 Blue Star Ltd. 23/24 Second Line Beach Madras 600 001 Tel: 23954 Telex: 379 Cable: BLUESTAR Caole: BLUESTAR Blue Star Ltd. Nathraj Mansions 2nd Floor Bistupur Jamshedpur 831 001 Tel: 38 04 Cable: BLUESTAR Telex: 240 INDONESIA INDONESIA BERCA Indonesia P.T. P.O. Box 496 1st Floor JL, Cikini Raya 61 Jakarta Tel: 56038, 40369, 49886 Telex: 2895 Jakarta IRAN Multi Corp International Ltd. Multi Corp International Ltd Avenue Soraya 130 P.O. Box 1212 IR-**Teheran** Tel: 83 10 35-39 Cable: MULTICORP Tehran Telex: 2893 mci th ISRAEL ISRAEL Electronics & Engineering Div of Motorola Israel Ltd. 17 Aminadav Street Tel-Aviv Tel: 36941 (3 lines) Cable: BASTEL Tel-Aviv Telex: 33569

JAPAN JAPAN Yokogawa-Hewlett-Packard Ltd. Ohashi Building 1-59-1 Yoyogi Shibuya-ku, Tokyo Tel: 03-370-2281/92 Telex: 232-2024YHP Cable: YHPMARKET TOK 23-724 Yokogawa-Hewlett-Packard Ltd. Nisei Ibaragi Bidg. 2-2-8 Kasuga Ibaragi-Shi Osaka **Usaka** Tel: (0726) 23-1641 Telex: 5332-385 YHP ()SAKA Yokogawa-Hewlett-Packard Ltd Nakamo Building No. 24 Kamisasazima-cho Nakamura-ku, **Nagoya** City Tel: (052) 571-5171 Tel: (052) 571-5171 Yokogawa-Hewlett-Packard Ltd. Nitto Bidg. 2-4-2 Shinohara-Kita Kohoku-ku **Yokohama 222** Tel: 045-032-1504 Telex: 382-3204 YHP YOK Yelogawa, 362-3204 YHP YUK Yokogawa-Hewiett-Packard Ltd. Chuo Bidg. Rm. 603 3. 2-Chome IZUMI-CHO Mito, 310 Tel: 0292-25-7470 KENYA Technical Engineering Services P.O. Box 18311 Nairobi, Kenya Tel: 57726 Cable: PROTON KOREA American Trading Company American Trading Company Korea I.P.O. Box 1103 Dae Kyung Bidg., 8th Floor 107 Sejong-Ro, Chongro-Ku, Seoul Tei: (4 lines) 73-8924-7 Gable: AMTRACO Seoul KUWAIT Al-Khaldiya Trading & Contracting Co. Al Soor Street Michaan Bldg No. 4 Kuwait Tel: 42 99 10 Cable: VISCOUNT

LEBANON Constantin E. Macridis Ciemenceau Street 34 P. 0. Box 7213 RL-Beirrut Tel: 220846 Telex: 21114 Leb Cable: ELECTRONUCLEAR Beirut MALAYSIA MECOMB Malaysia Ltd. 2 Lorong 13/6A Section 13 Petaling Jaya, **Selangor** Cable: MECOMB Kuala Lumpur MALAYSIA MOZAMBIQUE MOZAMBIQUE A.N. Goncalves, Lta. 162. 1° Apt. 14 Av. D. Luis Caixa Postal 107 Lourenco Marques Tel: 27091, 27114 Telex: 6-203 Negon Mo Cable: NEGON

Cable: NEGON NEW ZEALAND Hewlett-Packard (N Z.) Ltd. 94-96 Olxon Street P.O. Box 9443 Courtenay Place, Wellington Tel: 59-559 Telex: 3898 Cable: HEWPACK Wellington Cable: HEWPACK Wellington Hewiett-Packard (N.Z.) Ltd. Pakuranga Professional Centre 267 Pakuranga Highway Box 51092 Pakuranga Tel: 569-651 Cable: HEWPACK, Auckland NIGERIA The Electronics Instrumentatiofns Ltd. N6B/770 Oyo Road Oluseun House P.M.B. 5402 Ibadan Tel: 22325 Cable: THETEIL Ibadan The Electronics Instrumenta-lions Ltd. (TEIL) 16th Floor Cocoa House P.M.B. 5402 Ibadan Tel: 22325 Gable: THETEIL Ibadan

PAKISTAN

PAKISTAN Mushko & Company, Ltd. Dosman Chambers Abdullah Haroon Road Karachi 3 Tel: 511027, 512927 Cable: COOPERATOR Karachi

Mushko & Company, Ltd. 38B, Satellite Town **Rawalpindi** Tel: 41924 Cable: FEMUS Rawalpindi PHILIPPINES Princippines Electromex, Inc. 6th Floor, Amalgamated Development Corp. Bidg. Ayala Avenue, Makati, Rizai C.C.P.O. Box 1028 Makati, Rizai Tel: 86-18-87, 87-76-77. Cable: ELEMEX Manila

IE: Boiltowick Manila SiNCAPORE Mechanical & Combuston Engineering Company Pte. Ltd. 10/12, Jalan Kiang Red Hill Industrial Estate Singapore, 3 Tel: 84/151 (7 Ines) Cable MECOMB Singapore (Pte.) Ltd. BW. 2: 6th FLOOR, Jalan Bukut Merah Singapore 3 Singapore SOUTH AFRICA

Hewlett-Packard South Africi (Pty.), Ltd Hewlett-Packard House Daphne Street. Wendywood Sandton, Transvaal 2001 Tel: 802-1040 Celex: SA43-4782JH Cable: HEWPACK Hewlett-Packard South Africa (Pty.). Ltd. Bree Street Cape Town Tel: 2-6941/2/3 Cable: HEWPACK Cape Town Telex: 0006 CT Telex: 0006 CT Hewlett-Packard South Africa (Pty). Ltd. 641 Ridge Road, Ourban PO. Box 99 Overport, Natal Telex: 567954 Cable: HEWPACK

TAIWAN Hewlett-Packard Taiwan 39 Chung Shiao West Road Sec. 10 Verses Insurance Corp. Bidg. 7th Floor **Taipei** Tel: 389160.1.2, 375121. Ext. 240-249 Telex: TP824 HEWPACK Taipei HEWTPACK Taipei Hewlett-Packard Taiwan 38. Po-Ai Lane. San Min Chu. **Kaohsiung** Tei: 297319 THALLAND UNIMESA CO., Ltd. Eisom Research Building Banglak Sukumvit Ave. Bangkok Tel: 932387, 930338 Cable: UNIMESA Bangkok UGANDA Uganda Tele-Electric Co., Ltd P.O. Box 4449 Kampala Cable: COMCO Kampala VIETNAM Peninsular Trading Inc P.D. Box H-3 216 Hien-Vuong Saigon Tel: 20-805, 93398 Cable: PENTRA, SAIGON 242 ZAMBIA ZAMBIA R.J. Tilbury (Zambia) Ltd. P.O. Box 2792 Lusaka Zambia. Central Africa Tel: 73793 Cable: ARJAYTEE, Lusaka

MEDITERRANEAN AND MIDDLE EAST COUNTRIES NOT SHOWN PLEASE CONTACT: Hewlett-Packard S.A. Mediterranean and Middle Medilerranean and Middle East Operations 35, Kolokotroni Street Platia Kefallariou GR-Kifissia-Athens Telex: 21-6588 Cable: HEWPACKSA Athens OTHER AREAS NOT LISTED. CONTACT Hewlett-Packard Export Trade Company 3200 Hillview Ave. Palo Alto. California 94304 Tel. (415) 493-1501 TWX: 910-373-1267 Cable: HEWPACK Palo Alto Telex. 034-8300, 034-8493



17 Mar

P/N 09830-90004

MICROFICHE NO. 09830-99004

PRINTED IN U.S.A. APR. 4, 1975 OPERATING MANUAL

11270B MATRIX OPERATIONS ROM